


SmartPick Compatibility Document

10.12.19 B.Walter

This document lists the compatibility of the SmartPick software releases to the various HW revisions.

 = The indicated software releases are compatible to the indicated hardware revision

Dev	Rev	SmartPick Software Release								
		to 6.9.8.7	6.9.8.8 - 6.9.8.9	7.0.0 - 7.0.0.1	7.0.0.2 - 7.0.5.3	7.0.5.4	7.0.6 - 7.0.7.3	7.0.8 - 7.0.8.6	7.0.9...	
MB	01									
	02									
	03									
	04									
	05									
	06									
	07						Note 1			
	08						Note 2	Note 2		
	09						Note 2	Note 2		
PB	01									
	02									
	03									
	04									
	05									
	06				Note 3					
	07				Note 3					
	08				Note 3					
	09				Note 3					
	10				Note 3					
RB	01									
	02									
	03									
	04									
	05									
	06									
	07									
	08									
	09									
TB	01									
	02									
	03									
CB	01									
	02									
	03									
IOB	01									
DB	01									
	02									
SB	01									
	02									

Note 1: Software prior to 706 cannot be used with MBs Rev07 or newer since the new Bluetooth module is not correctly recognised.

Note 2: If Software 706 to 7086 is used together with MB Rev08 or newer, the status display of the service interface gives wrong main board supply readings. However, this doesn't have any other adverse effects.

Note 3: Rev. 6 and newer power boards exhibit larger current measurement offsets. SW Rev. 7.0.0.2 or newer MUST be used with these boards. Older SW revisions don't compensate these offsets. This may lead to inaccurate current measurements.